



I'm not robot



Continue

Change color of image photoshop

Using coloring layers, we will convert a color photo to black and white. Since the adjustment layers do not damage the original image, we will go back and color it in the selective areas of the image. The painting areas of these black and white photos are a quick and effective way to simulate the technique. With Photoshop, it's easy to make realistic-looking color changes and add patterns to an object. The tutorial object will be a tee shirt to be made in various colors and patterns of multiple shirts. The instructions in this article apply to Adobe Photoshop CC 2019. To follow, you need a t-shirt image and a pattern. In Photoshop, open the t-shirt image file and save it with a new name by choosing File > Save. In the pop-up window, type shirt_neutral in the text field, and then Color_Pattern to the text folder, then select Photoshop for the format and choose Save. Do the same with the pattern file, just save pattern_argyle (or the pattern you selected.). At the bottom of the Layers panel, select Create New Fill or Adjustment Layer, and then choose Tone/Saturation from the drop-down menu. This causes the Adjustments panel to appear. Place a check in the Colorize check box. To make the shirt blue, type Tone text field 204, Saturation text field 25, and Lightness text field 0. The file must now be given a new name. Choose File > Save, and change the name in the pop-up window shirt_blue the Color_Pattern to go to the file folder. then select Photoshop for the format and choose Save. To make more shirts of various colors, repeat the process, changing Hue, Saturation and Lightness repeatedly, and save each new shirt color with a new name in the Color_Pattern folder. Before you can apply a new pattern, you must define it. In Photoshop, choose File > Open, Color_Pattern the pattern you selected in the open folder, and then choose Open. A pattern image is displayed. Choose Define Pattern > Edit. In the Name text field, in the Pattern Name dialog box, press argyle (or whatever happens to your pattern), and then press OK. You don't need a file to stay open, so choose File > Close. Open a file that contains one of the shirt images. and with the Quick Selection tool. If this tool does not appear in the Tools panel, select and hold the Magic Wand Tool to see and select the Quick Selection tool. The quick selection tool works like a brush to quickly select fields. Click and drag the shirt. If you miss an area, just keep painting to add it to the existing selection. If you paint beyond the area, press and hold Alt (Windows) or Option (Mac OS) to paint what you want to delete. You can also change the size of the tool by repeatedly pressing the right or left footer. Now is the time to apply the defined pattern to the form. If the shirt is selected, select and hold the Create New Fill or Adjustment Layer button at the bottom of the Layers panel and select Pattern. The Pattern Fill dialog box should show the new pattern. If not, select the arrow just to the right of the pattern preview and select the pattern. The Fill dialog box also allows you to scale the pattern to the desired size. You can type a number in the scale area, or you can select the arrow just to the right of it to adjust the size with the slider, and then select OK. When the Pattern Fill layer is selected, right-click and select the blending options and change the blending mode in the drop-down menu to Multiplication. You can also try different blending modes to see how it affects the pattern. To save the new shirt, go to File > Save and type shirt_argyle name. Know that Photoshop is a default set of patterns to choose from. You can also use patterns for use. Before making this shirt, I downloaded a free set of plaid patterns. Click on the links below to download this plaid pattern and other free patterns and learn how to install them for use in photoshop. Continue to learn how to create your own custom patterns. To create a custom pattern in Photoshop, create a small canvas of 9 x 9 pixels, and then use the Zoom tool to zoom in 3200 percent. Create a simple design using the Pen tool. Define the design as a pattern by choosing Define Pattern > Edit. In the Pattern Name pop-up window, name the pattern diagonal and select OK. The pattern is now ready to use. A custom pattern is applied like any other pattern. To edit the custom pattern, see step 13, but instead select the pattern you created. You can continue to create multiple shirt colors and patterns for desire in your hearts. Thank you for the news! Tell me why! Photoshop is undoubtedly one of the best image editors available there. Packs great tools to allow you to re-prepare and enhance your photos. Almost anything you want to do with your photos can be done using Photoshop. It includes basic tasks, such as resizing your photos, and some advanced tasks, such as applying various effects, such as mirror effects, to your images. It's pretty easy to perform these tasks in the app, but you can definitely use some help to do faster tasks. When you upload a file to a website or want to send a photo to someone and it's a little too large, you need to change the size of the image to suit their needs. Photoshop helps you resize your photos quickly and easily using multiple size units and options. Open your photo in Photoshop on your computer. Click the Picture menu at the top and select Picture Size. Under Pixel Dimensions, you can change the Width and Height values for your photo. Set it the way you want, and from the drop-down menu next to your values, click Make sure of it. Then click OK. Maintains the width or height of the photo (but does not change both) aspect ratio. However, if you do not want it, then Proportions option in the resize panel. Crop Your Photos in Photoshop If there are some additional items you don't need, you might want to crop them. Cropping allows you to prevent only the selected part of your photo from deleting everything else. Photoshop lets you crop using both manual and pre-filled values. With your photo open in Photoshop, click the crop icon in the tools list. Click on your photo and you need to select the tracks you want to keep. When he's done, click the icon highlighted in the screenshot below to save the changes. If you want to crop the photo to a certain size, you can enter dimension values in pixels at the top of your screen. You can also choose one of the default options for cropping your photo (for example, the frame crop option that helps you crop your photo squarely, and so on. When it comes to translating a photo in Photoshop, Translate Image in Photoshop, there are two ways to do it. You can either flip the entire picture that will flip everything you see on your screen, or you can flip a specific layer. The second would be to translate its contents not only within this layer, but within the entire image. To flip the entire picture in Photoshop, click the Picture menu at the top and choose Rotate An Image. Here you will see two options: Flip Canvas Horizontally and Flip Canvas Vertically. You can choose any of these options to translate your photo. If you only want to flip a specific layer, select it, click the Edit menu at the top, select Transform, and choose Flip Horizontal or Flip Vertical. Photoshop Blur helps you hide sensitive information in your photos in Photoshop Blur, and Photoshop has multiple tools to do this. You can select the area you want to blur, and then select one of the options to blur. If you want to blur the entire photo, click the Filter menu at the top, select Blur, and select one of the available blur options. If you apply a blur effect and don't like it, press Ctrl + Z to undo the effect. To blur a specific area in your photo, use the selection tool to select the area first. Then use the same Filter > Blur menu to blur your photo. How to Zoom in and Out in Photoshop High-resolution photos often require you to zoom in to see specific sections that are not clearly seen in normal viewing mode. Photoshop greatly provides zooming in and out, and there are several ways to access the feature. With your photo open in the app, click the zoom tool in the list of tools on the left. Click where you want to zoom in on your photo and the photo will magnify itself. Another way to zoom in or out is to Click the View menu at the top and choose Zoom In or Out, depending on what you want to do. Rotate a Photo in Photoshop, if your photo is in portrait layout but needs to be horizontal, or vice versa, you can correct it by rotating it in Photoshop. You have multiple aspects to rotate your photo application and it is quite easy to do. Your photo then adapts the orientation you selected in the app. Open the picture you want to rotate in Photoshop. Click the Edit menu at the top and choose Convert. You'll see the three rotation options as follows: Rotate 180 – rotates your photo 180 degrees 90 CW – rotates your photo clockwise 90 degrees Rotate 90 CCW – rotates your photo 90 degrees counterclockwise and be sure to save your picture after rotating it. Photo Mirroring in Photoshop A mirror effect can be achieved by combining multiple tools into a workaround in the app. Right-click the Background layer and choose Repeating Layer. Click the Picture menu at the top and choose Canvas Size. Change the dimension unit to Percentage and enter 200 in the Width box. Then click the center left icon and click OK. Now you'll have the same two pictures on your screen. Click the edit menu and choose Convert following Flip Horizontal. Your photo should be projected now. Photoshop has tremendous features to help you edit and retouch your photos. Using it to enhance images of your photos? What is your favorite tool in the app? Let us know the comment below! Below!